

# APIs Documents.

## SEND SINGLE / BULK SMS API

[https://sms.lrt.com.pk/api/sms-single-or-bulk-api.php?  
 username=<Username>&password=<Password>&apikey=<APIKEY>&sender=<Sender>&phone=<Phone>&type=<Language>&message=<Message>](https://sms.lrt.com.pk/api/sms-single-or-bulk-api.php?username=<Username>&password=<Password>&apikey=<APIKEY>&sender=<Sender>&phone=<Phone>&type=<Language>&message=<Message>)

PARAMETER	DESCRIPTION
Username	Your login username. (Required)
API Password	Your API Password. (Required)
API KEY	APIKEY provided by admin to you. (Required)
Sender	Sender name provided by admin to you. (Required)
Phone	Phone number(s) for single sms you need to pass phone e.g. 923006016934 and for bulk sms you to pass more than one numbers separated by commons e.g. 923006016934,923336016934. In Bulk sms you can send messages upto 10 phone numbers at a time. (Required)
Type	Message type can be Urdu or English (Required)
Message	Your message content. If type is Urdu you can send upto 335 character long message and if type is English you can send upto 765 characters long message.

### EXAMPLE SINGLE SMS:

[https://sms.lrt.com.pk/api/sms-single-or-bulk-api.php?  
 username=ABC&password=Abc&sender=SENDER&apikey=APIKEY&phone=923006016934&type=English&message=Hello](https://sms.lrt.com.pk/api/sms-single-or-bulk-api.php?username=ABC&password=Abc&sender=SENDER&apikey=APIKEY&phone=923006016934&type=English&message=Hello)

### EXAMPLE BULK SMS:

https://sms.lrt.com.pk/api/sms-single-or-bulk-api.php?  
username=ABC&password=Abc&sender=SENDER&apikey=APIKEY&phone=92300  
6016934,923336016934&type=Urdu&message=Hello

**REQUEST RESPONSE:**

Your Message is sent, MSISDN 2, Cost 2

## CHECK BALANCE API:

https://sms.lrt.com.pk/api/balance.php?  
username=<Username>&password=<Password>

PARAMETER	DESCRIPTION
Username	Your login username. (Required)
API Password	Your API Password. (Required)
API KEY	APIKEY provided by admin to you. (Required)

## EXAMPLE SINGLE SMS:

https://sms.lrt.com.pk/api/balance.php?username=ABC&password=ABC&apikey=APIKEY

## REQUEST RESPONSE:

Your credit is 495376 & your credit limit is 495376

## CHECK SMS DELIVERY API:

https://sms.lrt.com.pk/api/dlr.php?  
username=<Username>&password=<Password>&apikey=<APIKEY>  
&phone=<Phone>

PARAMETER	DESCRIPTION
Username	Your login username. (Required)
API Password	Your login password. (Required)
API KEY	APIKEY provided by admin to you. (Required)
Phone	Phone number which sms status you want to know.

**EXAMPLE SINGLE SMS:**

https://sms.lrt.com.pk/api/balance.php?  
username=ABC&password=ABC&apikey=2abc78hd52dr  
&phone=923006016934

**REQUEST RESPONSE:**

Your message status for 923006016934 is Sent.

**NEW SMS POST JSON API:**

https://sms.lrt.com.pk/api/new-sms-api.php


POST PARAMETER	DESCRIPTION
Username	Your login username. (Required)
Api Password	Your login password. (Required)
API KEY	APIKEY provided by admin to you. (Required)
Sender	Sender name provided by admin to you. (Required)
sms_data	[{"phone":923422988522,"type":"urdu","message":"Test Message From Here."},{ "phone":923006016934,"type":"urdu", "message":" Test Message From Here."}]

**EXAMPLE NEW SMS API:**


https://sms.lrt.com.pk/api/new-sms-api.php

**JSON REQUEST RESPONSE:**

[{"cost":7,"id":2061164},{ "cost":2.5,"id":2061165},{ "cost":4.5,"id":2061166}]

0300 6016-934 

WWW.LRT.COM.PK 

LUQMANRASUL@LIVE.COM 

20/A TEHSIL CHOWK MULTAN. 